

Durcissement post-installation

[virtualisation](#), [VM](#), [Debian](#), [post-install](#), [durcissement](#)

Une fois l'installation d'un OS "de base" (voir [cette page](#)), et la configuration post-install (voir [cette page](#)) effectuées, nous allons appliquer le durcissement de l'OS.

Hooks APT

Afin de pouvoir repasser les partitions /boot et /usr en read / write, et la partion /tmp en exec lors de l'installation de nouveaux paquets ou lors de l'upgrade de l'OS, nous ajoutons des hooks pour APT.

Nous créons le fichier 00apt

```
# vi /etc/apt/apt.conf.d/00apt
```

Nous y ajoutons ceci

```
DPkg::Pre-Invoke {
    "mount -o remount,rw /boot";
    "mount -o remount,rw /usr";
    "mount -o remount,exec /tmp";
};
DPkg::Post-Invoke {
    "mount -o remount,ro /boot";
    "mount -o remount,ro /usr";
    "mount -o remount,noexec /tmp";
};
```

Fstab

Nous éditons le fichier fstab

```
# vi /etc/fstab

# /etc/fstab: static file system information.
#
# Use 'blkid' to print the universally unique identifier for a
# device; this may be used with UUID= as a more robust way to name devices
# that works even if disks are added and removed. See fstab(5).
#
# <file system>          <mount point>   <type>  <options>
<dump> <pass>
/dev/mapper/vg_sys-lv_root /               btrfs   defaults
0          0
# /boot was on /dev/sda1 during installation
```

UUID=8077782c-de8c-4850-88ca-d93a1b706979	/boot	ext4		
ro,nodev,nosuid,noexec	0	2		
/dev/mapper/vg_sys-lv_tmp	/tmp	btrfs		
relatime,nodev,nosuid,noexec	0	0		
/dev/mapper/vg_sys-lv_usr	/usr	btrfs	ro,nodev	
0	0			
/dev/mapper/vg_sys-lv_log	/var/log	btrfs		
nodev,nosuid,noexec	0	0		
/dev/mapper/vg_sys-lv_audit	/var/log/audit	btrfs		
nodev,nosuid,noexec	0	0		
/tmp	/var/tmp	none		
rw,noexec,nosuid,nodev,bind	0	0		
/dev/mapper/vg_sys-lv_swap	none	swap	sw	
0	0			

From: <https://wiki.grohub.org/> - **Grohub wiki**

Permanent link: <https://wiki.grohub.org/infrastructure/virtualisation/vms/debian/post-install-durcissement>

Last update: **01/11/2020 16:30**

